

RecLinkAPP

WORKFLOW

for SCENE
version 6.1 and previous



Contacts

Gexcel Srl
Central Administration | Sales & Lab
c/o CSMT, Via Branze 45, I-25123 Brescia, Italy

Registered Office | R&D Lab
c/o Polaris Science and Technology Park
Loc. Piscinamanna, I-09010, Pula (CA), Italy

OVERVIEW


Thanks for choosing RecLinkAPP for SCENE!



Follow just few quick steps for an easy installation and look at the suggested workflow!

SETTINGS


1. Install JRC 3D Reconstructor (every package).
2. Once you know your PC OS, choose:
 - a. 32 or 64 bit version
 - b. your preferred language (now available ENG, ITA)
3. Drag the *.fpp file into SCENE.



 GexcelFaroSceneApp_Eng_x64.fpp


ACTIVATION

4. Go to: Tools → Apps → Activate GexcelFaroSceneApp.



ACTIVATION



5. See in the SCENE toolbar the “Gexcel” menu ready to be used.



WORKFLOW

From SCENE to JRC 3D Reconstructor


1. Import your scans or open your projects in SCENE.
2. Select your JRC 3D Reconstructor package in the "Gexcel" menu.



WORKFLOW

From SCENE to JRC 3D Reconstructor


3. Select the scans to send to JRC 3D Reconstructor.



WORKFLOW

From SCENE to JRC 3D Reconstructor


4. Select the points subsampling.
5. Select the color options: only color or color&reflectance.




WORKFLOW

From SCENE to JRC 3D Reconstructor

6. Create a new folder where the JRC 3D Reconstructor project will be generated.





7. Open your JRC 3D Reconstructor project and work on it.



WORKFLOW



From JRC 3D Reconstructor to SCENE WebShare

1. Export your JRC 3D Reconstructor point cloud in .e57 format.




WORKFLOW

From JRC 3D Reconstructor to SCENE WebShare




WORKFLOW

From JRC 3D Reconstructor to SCENE WebShare



2. Use the *Create WebShare data* command and bring your JRC 3D Reconstructor point cloud to SCENE WebShare.





www.gexcel.it

T. (+39) 030 65 95 001

info@gexcel.it

sales@gexcel.it